The Parallel File System and I/O

SNUG TechTalk

SciNet, Toronto



File system recap



- 1790 1TB SATA disk drives, for a total of 1.4PB
- Two DCS9900 couplets, each delivering 4-5GB/s read/write access to the drives
- Single *GPFS* file system on TCS and GPC
- I/O goes over Gb ethernet network on GPC (infiniband on TCS)
- File system is parallel!



location	quota	block-size	time-limit	backup	devel	comp
/home	10GB	256kB	unlimited	yes	rw	ro
/scratch	X TB	4MB	3 months	no	rw	rw

- There are quotas
- Home read-only from compute nodes!
- Big block sizes: small files waste space
- Issues are common to parallel file systems (Lustre, etc.) present in most modern supercomputers.
- Scratch quota per user oversubscribes disk space, so only for when you *temporarily* really needs a lot of disk space.
- Most users will need much less.



File system recap

Scratch Policies


- Scratch is intended for active jobs (e.g. writing checkpoints and data during a run).
- Files are purged after 3 months (may need to reduce this to 2 months soon).
 - Quotas on space and number of files will be tightened after this week's shutdown.




The file system is parallel, what does that mean?














Basic Components







Basic Components








How can we push the limit?



How can we BREAK the limit?



- Optimal for large shared files.
- Behaves poorly under many small reads and writes.
- Your use of it affects everybody! (Different from case with CPU and RAM which are not shared.)
- How you read and write, your file format, the number of files in a directory, and how often you ls, can all affect every other user!
- The file system is shared over the ethernet network on GPC: Hammering the file system can hurt process communications.
- File systems are not infinite! Bandwidth, metadata, IOPS, number of files, space, ...

Parallel File System and I/O - 8 Sept 2010 **I** p. 7/20

- Think of your laptop/desktop with several people simultaneously doing I/O, doing ls on directories with thousands of files ...
- 2 jobs doing simultaneous I/O can take *much* longer than twice a single job duration due to disk *contention* and directory *locking*.
- SciNet: 500 users doing I/O from 4000 nodes. That's a lot of sharing and contention!





Some Numbers

- 466 TB on scratch
- Over 500 users you do the math!
- Want >25% free at any given time (systems can write 0.5 PB per day!)
- 100 MB/s: maximum possible read/write speed from a node if there is nothing else running on system
- 1 MB/s: average expected read/write speed from a node when system is fully utilized



How to make the file system work for rather than against you



Make a Plan!

Make a plan for your data needs:

- How much will you generate,
- How much do you need to save,
- And where will you keep it?
- Note that /scratch is *temporary* storage for 3 months or less.
- Options?
 - Save on your departmental/local server/workstation (it is possible to transfer TBs per day on a gigabit link);
 - Apply for a project space allocation at next RAC call (but space is very limited);
 - 3. Buy tapes through us (\$100/TB) and we can archive your data to tape; HSM possibility within next 6 months;
 - 4. Change storage format.

Monitor and control usage

- Minimize use of filesystem commands like ls and du.
- Regularly check your disk usage using /scinet/gpc/bin/diskUsage.
- Warning signs which should prompt careful consideration:
 - More than 100,000 files in your space
 - Average file size less than 100 MB
- Monitor disk actions with top and strace
- RAM is always faster than disk; think about using ramdisk.
- Use gzip and tar to compress files to bundle many files into one
- Try gziping your *data* files. 30% not atypical!
- Delete files that are no longer needed
- Do "housekeeping" (gzip, tar, delete) regularly.

Change storage format

- Write binary format files faster I/O and less space than ASCII files
- Use parallel I/O if writing from many nodes NetCDF, HDF5, MPI-IO
- Maximize size of files. Large block I/O optimal!
- Minimize number of files Makes filesystem more responsive!
- Attend the parallel I/O course coming soon! https://support.scinet.utoronto.ca/courses

Don'ts:

- Don't write lots of ASCII files. Lazy, slow, and wastes space!
- Don't write many hundreds of files in a 1 directory. Hurts responsiveness!
- Don't write many small files (< 10MB). System is optimized for large-block I/O!

Summary

- Make a data plan.
- Regularly check disk usage with /scinet/gpc/bin/diskUsage.
- RAM is always faster than disk: ramdisk.
- Write binary files.
- Use parallel I/O if writing from dozens of nodes.
- Use gzip and tar.
- Delete unneeded files.
- Maximize size of files.
- Do housekeeping regularly.
- Monitor disk actions with top and strace.
- Visit parallel I/O course coming soon!
- Make an appt to talk with our analysts about your I/O.

Don'ts

- Do not write lots of ASCII files.
- Do not write many hundreds of files in a single directory.
- Do not write many small files.
- Minimize use of file system commands like Is and du. Control of the system commands like Is and du.

Extras slides: examples



Ramdisk example

	northrup@aries:pts/11:~
<u>F</u> ile <u>E</u> dit <u>V</u> iew <u>T</u> erminal Ta <u>b</u> s <u>H</u> elp	
<pre>#!/bin/bash #MOAB/Torque submission script for SciNet #PBS -l nodes=1:ppn=8,walltime=24:00:00 #PBS -N ramdisk-test</pre>	GPC
cd \$PBS_0_WORKDIR mpirun -np 8 ./mycode	
	northrup@aries:pts/1:~
<u>F</u> ile <u>E</u> dit <u>V</u> iew <u>T</u> erminal Ta <u>b</u> s <u>H</u> elp	
<pre>#!/bin/bash #MOAB/Torque submission script for SciNet #PBS -l nodes=1:ppn=8,walltime=24:00:00 #PBS -N ramdisk-test</pre>	GPC
<pre># stage-in mkdir -p /dev/shm/\$USER cp -a \$PBS_0_WORKDIR/ /dev/shm/\$USER cd /dev/shm/\$USER</pre>	
#run code mpirun - <mark>np 8</mark> ./mycode	
# stage-out tar -czf \$PBS_0_WORKDIR/output.tar.gz /dev rm -Rf /dev/shm/\$USER	v/shm/\$USER

Top example

							I	orthru	ıp@gpc-logindm01/~	
<u>F</u> ile <u>E</u>	<u>a</u> dit <u>V</u> iew	<u>T</u> erm	ninal	Ta <u>b</u> s	<u>H</u> elp					
Tasks:	: 184 tota): 0.7%u: 8174984	al, s, 0 k tot	1 r).9%s al,	unning sy, 0. 67088	, 183 0%ni, 04k u	sleepi 98.1%i sed, 1	.ng, .d, (.46618	0 st 0.0%wa		
PID	USER	PR	NI	VIRT	RES	SHR S	%CPU	%MEM	TIME+ COMMAND	
3470	root	Θ	-20	2453m	1.1g	21m S	8.3	14.0	2664:48 mmfsd	
23606	nolta	18	Θ	4528	1312	508 D	6.0	Θ.Θ	0:02.30 zip	
1	root	15		10348	708	592 S	0.0		0:04.50 init	
2	root	RT	- 5	Θ	Θ	0 S			0:03.60 migration/0	
3	root	34	19	Θ	Θ	0 S	0.0		0:00.30 ksoftirqd/0	
4	root	RT	- 5	Θ	Θ	0 S	0.0	0.0	0:00.00 watchdog/0	
5	root	RT	- 5	Θ	Θ	0 S	0.0	0.0	0:07.54 migration/1	
6	root	34	19	Θ	Θ	0 S	0.0	0.0	0:00.73 ksoftirqd/1	
7	root	RT	- 5	Θ	Θ	0 S	0.0	Θ.Θ	0:00.00 watchdog/1	
8	root	RT	- 5	Θ	Θ	0 S	0.0	Θ.Θ	0:04.60 migration/2	
	root	34	19	Θ	Θ	0 S	0.0	0.0	0:02.13 ksoftirqd/2	
10	root	RT	- 5	Θ	Θ	0 S	0.0	0.0	0:00.00 watchdog/2	
11	root	RT	- 5	Θ	Θ	0 S	0.0	0.0	0:06.93 migration/3	
12	root	34	19	Θ	Θ	0 S	0.0	Θ.Θ	0:08.96 ksoftirqd/3	
13	root	RT	- 5	Θ	Θ	0 S	0.0	Θ.Θ	0:00.00 watchdog/3	
14	root	RT	- 5	Θ	Θ	0 S	0.0	0.0	0:04.00 migration/4	
15	root	34	19	Θ	Θ	0 S	0.0	Θ.Θ	0:00.28 ksoftirqd/4	
16	root	RT	- 5	Θ	Θ	0 S	0.0	Θ.Θ	0:00.00 watchdog/4	
17	root	RT	- 5	Θ	Θ	0 S	0.0	0.0	0:06.26 migration/5	
18	root	34	19	Θ	Θ	0 S	0.0	0.0	0:09.94 ksoftirqd/5	
19	root	RT	- 5	Θ	Θ	0 S	0.0	0.0	0:00.00 watchdog/5	
20	root	RT	- 5	Θ	Θ	0 S	0.0	0.0	0:04.22 migration/6	
21	root	34	19	Θ	Θ	0 S	0.0	0.0	0:00.42 ksoftirqd/6	
22	root	RT	- 5	Θ	Θ	0 S	0.0	0.0	0:00.00 watchdog/6	
23	root	RT	- 5	Θ	Θ	0 S	0.0	Θ.Θ	0:07.08 migration/7	

Tar/gzip example

						northrup@gpc-f101n084//scratch/northrup/temp/osu_network
<u>F</u> ile	<u>E</u> dit	<u>V</u> iew	<u>T</u> erminal	Ta <u>b</u> s	<u>H</u> elp	
			f101n084	/scra	tch/n	orthrup/temp]\$ tar -czvf file.tar.gz osu_network/
	netwo					
		rk/os				
			u_alltoal			
			u_bcast.c			
			u_bibw.c			
			u_bw.c			
			u_get_bw.			
			u_mbw_mr.			
			u_multi_l			
			u_put_bib u_put_bw.			
					tch/n/	orthrup/temp]\$ ls
			su_networ		cen7 no	ior chi up/ cempja ca
					tch/n	orthrup/temp]\$ tar -tf file.tar.gz
	netwo		10111004	/ 5014	cen, m	iorentup/cempjo/car -er rice.car.gz
		rk/os	u.h			
			u alltoal	1.c		
			u bcast.c			
			u bibw.c			
			u bw.c			
			u_get_bw.	с		
			u_mbw_mr.			
osu	netwo	rk/os	u_multi_l	at.c		
osu	netwo	rk/os	u_put_bib	w.c		
osu	netwo	rk/os	u_put_bw.	С		
[nor	thrup	@gpc-	f101n084	/scra	tch/n	<pre>orthrup/temp]\$ tar -xzf file.tar.gz osu_network/osu_get_bw.</pre>
					tch/n	orthrup/temp]\$ ls
file	e.tar.	gz o	su_networ	k		

I/O speed for ASCII

Writing 128M doubles:

/scratch:

ASCII	173 s
binary	6 s

/dev/shm:

ASCII	174 s
binary	1s (!)



File system at a glance

